

NAME

pce-img – the PCE disk image utility

SYNOPSIS

pce-img create [*options*] [*output-file*]

pce-img convert [*options*] [*input-file*] [*options*] [*output-file*]

DESCRIPTION

pce-img(1) is used to create and convert disk image files.

OPTIONS

-c, --cylinders *c*

Set the number of cylinders.

-C, --min-cluster-size *size*

Set the minimum cluster size for QED images. The default is 0.

-f, --offset *offset*

Set the starting offset of the disk image for formats that support it.

-g, --geometry *c h s*

Set the disk geometry. This is the same as using the **-c**, **-h** and **-s** options.

-h, --heads *h*

Set the number of heads.

-i, --input *filename*

Set the input file name.

-m, --megabytes *size*

Set the disk size in MiB.

-n, --size *blocks*

Set the disk size in 512 byte blocks.

-o, --output *filename*

Set the output file name.

-q, --quiet

Be quiet.

-s, --sectors *s*

Set the number of sectors per track.

-w, --cow *filename*

Set the COW file name.

--help Print usage information.

--version

Print version information.

EXAMPLES

Create a 1 GiB PIMG image:

```
$ pce-img create -m 1024 -o image.pimg
```

Create a 10 MB PIMG image

```
$ pce-img create -g 306 4 17 -o image.pimg
```

Convert a PIMG image to a raw image

```
$ pce-img convert source.ping dest.img
```

SEE ALSO

pce-ibmpc(1), pce-macplus(1), pfdc(1)

AUTHOR

Hampa Hug <hampa@hampa.ch>